

*R*TIME Dynamic Message Summary Display*

Brent Young
SCIENTECH, LLC

August 2004

*R*TIME System Files*

❖ System Files include:

- System Messages
- User Messages
- Alarm Messages
- SOE Messages
- 16 System Event Files

❖ System Files reside in the %RTIMEHOME%\unit\messages\local directory.

Message Retrieval Display

- ❖ Existing Message Retrieval Display
 - Requires user action for any output.
 - Report driven output.

PPC-A

ACTIVE

PLANT MODE
SHUTDOWN

ALM

Message Retrieval

Health

RX/PWR

HR/CC

8/02/04

Retrieve

File Info

MESSAGES

INT

CTMT

RAD

11:48:32

MESSAGE FILE:
(Select one of the Primary files or a Secondary file.)

PRIMARY USER MESSAGES

PRIMARY SYSTEM MESSAGES

PRIMARY ALARM MESSAGES

PRIMARY SOE MESSAGES

PRIMARY SYSTEM EVENT FILE 1

PRIMARY SYSTEM EVENT FILE 2

PRIMARY SYSTEM EVENT FILE 3

PRIMARY SYSTEM EVENT FILE 4

PRIMARY SYSTEM EVENT FILE 5

PRIMARY SYSTEM EVENT FILE 6

PRIMARY SYSTEM EVENT FILE 7

PRIMARY SYSTEM EVENT FILE 8

PRIMARY SYSTEM EVENT FILE 9

PRIMARY SYSTEM EVENT FILE 10

PRIMARY SYSTEM EVENT FILE 11

PRIMARY SYSTEM EVENT FILE 12

PRIMARY SYSTEM EVENT FILE 13

PRIMARY SYSTEM EVENT FILE 14

PRIMARY SYSTEM EVENT FILE 15

PRIMARY SYSTEM EVENT FILE 16

Secondary Files

START DATE/TIME: (MM/DD/YYYY HH:MM:SS.MIL)

END DATE/TIME: (MM/DD/YYYY HH:MM:SS.MIL)

FILTER:

Dynamic Message Summary Display

- ❖ **Dynamic Message Retrieval Display Features**
 - Dynamically updates the display based on new messages.
 - Allows user to filter data by time, string, and file.
 - Allows user to sort messages chronologically or reverse chronologically.
 - Allows user to create a printable report of the displayed data.
 - Allows paging through the displayed messages.

Dynamic Message Summary Display

❖ Dynamic Message Retrieval Display Features

- Allows user to see start/end time of the selected file.
- Allows user to customize aliases for R*TIME System event files.
- Allows user to customize which System Event file is loaded when coming from a specific display.

DATE	TIME	MESSAGE

START DATE/TIME:
 (MM/DD/YYYY HH:MM:SS.MIL)
8/12/2004 11:50:40.000

END DATE/TIME:
 (MM/DD/YYYY HH:MM:SS.MIL)
8/14/2004 11:50:40.000

FILTER:

CURRENT FILE:
System Messages

- File Info
- Create Report
- Change Sort
- Page 1
- ▲ ▼

Page 1 of 1
 Summary is empty

Custom Configuration

- ❖ Configuration is available via the MsgSummary.ini file. Located in the %RTIMEHOME%\data directory.
- ❖ Configuration allows:
 - Aliases on the R*TIME System Event Files.
 - Loading specified files when coming from a default display.

MsgSummary.ini File

- *
 - * MsgSummary.ini is used to configure the aliases for the SYSTEM EVENT file logs
 - * as well as define which file to default to when MsgSummary display is started
 - *
 - * The ALIAS defines the Aliases for the 16 SYSTEM EVENT files
 - * This is what is displayed in the Pick list
 - * This DISPLAY defines which file to default to when the MsgSummary is started from that specific display

MsgSummary.ini File (Cont.)

[FILE 1]

* SYSTEM EVENT FILE 1

ALIAS=DCC X

DISPLAY=DFRCS_MENU

[FILE 2]

* SYSTEM EVENT FILE 2

ALIAS=RAGEMS

DISPLAY=RAGEMS_MENU

[FILE 3]

* SYSTEM EVENT FILE 3

ALIAS=RWM

DISPLAY=RWM_MENU

*Continues Through 16